



KONICA MINOLTA

FTP Utility Ver.1.0

User's Guide

1 Foreword

1.1 About This Product

This software is a utility used for receiving data sent from compatible devices (multifunctional products) using the Scan to FTP operation.

When data is received from a multifunctional product, authenticates the user name and password, and saves the data in the specified receiving folder.

1.2 Trademarks and Registered Trademarks

KONICA MINOLTA and the KONICA MINOLTA logo are trademarks of KONICA MINOLTA HOLDINGS, INC.

All other product names are either trademarks or registered trademarks of their respective companies.

1.3 System Requirements

In order to use this software, the operating environment must meet the following specifications.

- Operating System
 - Windows 98 (Service Pack 1 or later), 98 Second Edition, or Me
 - Windows NT Workstation (Service Pack 6a or later)
 - Windows 2000 Professional (Service Pack 2 or later)
 - Windows XP Home Edition/Professional Edition
- Computer
 - PC/AT compatible machine (installed with a Pentium III or faster processor)
- Memory
 - 128 MB or more
 - 192 MB or more with Windows XP Home Edition/Professional Edition
- Available Hard Disk Space
 - 20 MB or more
- Compatible Devices
 - Refer to the ReadMe file.

1.4 Manual Structure

This manual consists of the following sections.


- Installing FTP Utility
 - This section provides the procedure for installing FTP Utility onto the computer.
- Uninstalling FTP Utility
 - This section provides the procedure for removing FTP Utility from the computer.
- Using FTP Utility
 - This section provides procedures for starting up FTP Utility and specifying settings for receiving data.

2 Installing FTP Utility


Installing the Software

The procedure for installing FTP Utility onto the computer is described below.


- 1 Double-click “FTPUtilitySetup.exe”.
A message indicating the beginning of the installation appears.
- 2 Click the [Next] button.




- 3 Read the license agreement, and then click the [Yes] button.




- 4 To change the installation location, click the [Browse] button, and then select the different installation location. To continue without changing the installation location, click the [Next] button.



- 5 Select the check boxes for the shortcuts that you wish to register, and then click the [Next] button.



- 6 Click the [Finish] button.
The installation is complete.




3 Uninstalling FTP Utility

Uninstalling the Software


The procedure for removing FTP Utility from the computer is described below.

On Windows XP Home Edition/Professional Edition

- 1 On the [Start] menu, click [Control Panel].
- 2 Click [Add or Remove Programs].



- 3 Click “FTP Utility”, and then click the [Change/Remove] button.



- 4 When the message requesting confirmation to delete the files appears, click the [OK] button.
FTP Utility is deleted.

4 Using FTP Utility

Starting Up FTP Utility

The procedures for starting up FTP Utility and specifying settings for receiving data are described below.

- ➔ On the [Start] menu, point to [KONICA MINOLTA], then [FTP Utility], and then click [FTP Utility].

After FTP Utility has been started up, the FTP Utility icon appears in the taskbar, located at the lower-right end of the desktop.



Note

When sending data using the Scan to FTP operation from a multifunctional product, FTP Utility must be started up on the computer receiving the data. Before sending the data, start up the software on the computer and specify the necessary settings, such as the folder where the data is to be saved.

FTP Utility Settings

In the FTP Utility Settings dialog box, settings for the following parameters can be specified.

| Parameter | Description |
|-------------|--|
| TCP Port | Specify the port for receiving the data. Normally, this setting will not need to be changed. |
| Root Folder | Specify the folder for saving data received from a multifunctional product using the Scan to FTP operation. To change the folder, click the [Browse] button, and the select a different folder. |
| FTP User | In order to receive data, specify the user name and password. When data is sent from a multifunctional product, these same settings must also be specified. To receive data from an anonymous user, select the "Anonymous" check box. To authenticate the user name and password when receiving data, type the appropriate settings in the "User" and "Password" boxes. The limitations on the number of characters that can be entered in the "User" and "Password" boxes differ depending on the multifunctional product, and a specific user name and password may be required. For details, refer to the User's Guide for the multifunctional product. |


Specifying FTP Utility Settings

- 1 Click the FTP Utility icon in the taskbar (at the lower-right end of the desktop), and then select [FTP Utility Settings].

The FTP Utility Settings dialog box appears.



- 2 Specify the necessary settings, and then click the [OK] button.



Quitting FTP Utility

- Click the FTP Utility icon in the taskbar (at the lower-right end of the desktop), and then select [Exit].

If Data Cannot Be Received Correctly

Check for the following.

- Has FTP Utility been started up?
- Have settings for the root folder (folder where received files are saved), user name, and password been correctly specified?



KONICA MINOLTA

<http://konicaminolta.com>